

Administration settings

Name	Description	Default Value
Can user access current orders	When selected, this user can access eServ Current Orders.	true
Current orders menu text	This value contains the text to display on the menu to access current orders.	Current Orders

Current orders list page options

Name	Description	Default Value
Current order list page name	This value specifies the web page to display for the current order listing. This page must exist in your Website or an error will occur	HOList.asp
List page header title	This value determines the header title shown in the upper right portion of the current orders list page.	Current Orders
List page title	This value determines the list page title shown in the center of the current orders list page.	Current Open Order Listing
List page instruction message text	This value determines the instruction text shown above the current open order listing box.	Click an order number link on the list below to display the order details.
List pay codes to show	This value determines the pay codes to include on the open order listing. Only those pay codes listed will be shown. Enter the pay codes, one at a time, with no spaces.	1234
List page status codes to display	This value determines the status codes to display in the current order listing. Enter the status codes, one at a time, with no spaces.	2456789B
Maximum days to show order as current	This value determines the maximum number of days from the order date an order will show on the current order list. Orders older than this number of days will not be shown on the list.	30
Show short PO on order list page	When selected, the short PO field will be shown on the current orders list page.	true
Short PO display name	This value contains the display name for the short PO field if shown on the current orders list page.	PO NUMBER
Show long PO on order list page	When selected, the long PO field will be shown on the current orders list page.	true
Long PO display name	This value contains the display name for the long PO field if shown on the current orders list page.	EXTENDED PO

List status code settings

Name	Description	Default Value
Status code 0 description	This value determines the description to display on the current orders list page for orders in status code 0.	On Hold
Status code 1 description	This value determines the description to display on the current orders list page for orders in status code 1.	Open
Status code 2 description	This value determines the description to display on the current orders list page for orders in status code 2.	Open
Status code 3 description	This value determines the description to display on the current orders list page for orders in status code 3.	Open
Status code 4 description	This value determines the description to display on the current orders list page for orders in status code 4.	Open
Status code 5 description	This value determines the description to display on the current orders list page for orders in status code 5.	Open
Status code 6 description	This value determines the description to display on the current orders list page for orders in status code 6.	Open
Status code 7 description	This value determines the description to display on the current orders list page for orders in status code 7.	Open
Status code 8 description	This value determines the description to display on the current orders list page for orders in status code 8.	Open
Status code 9 description	This value determines the description to display on the current orders list page for orders in status code 9.	Open
Status code A description	This value determines the description to display on the current orders list page for orders in status code A.	Open
Status code B description	This value determines the description to display on the current orders list page for orders in status code B.	Complete

History option settings

Name	Description	Default Value
History days to display as current orders	This value determines the number of days to consider history (jour-s) records as current orders. Remember that after orders are completed, they transfer to the history files. This value can be set to show the most recent completed orders.	7
History display message text	This value determines the text shown above the current order history display.	Recent completed/shipped orders:

Order detail page options

Name	Description	Default Value
Order detail page name	This value specifies the web page to display for the order detail display. This page must exist in your Website or an error will occur.	HOrder.asp
Order detail page header title	This value determines the header title shown in the upper right portion of the order detail page.	Order Detail
Order page title	This value determines the title shown on the order detail page. The value is shown before the order number.	Our Order Number:
Our order number text	This value contains the text for the our order number display shown on the order detail page.	Our Order Number:
Order detail instruction message text	This value determines the instruction text shown above the order detail on the order detail page.	Order Detail
Show short PO on order	When selected, the short PO will be shown on the order detail page.	true
Short PO display name	This value contains the display name for the short PO field if shown on the order detail page.	PO NUMBER
Show long PO on order detail page	When selected, the long PO field will be shown on the order detail page.	true
Long PO display name	This value contains the display name for the long PO field if shown on the order detail page.	EXTENDED PO
Show who called name	If selected, this option will show the who called special on the order detail page header strip.	true
Who called display name	This value contains the display name for the who called field if shown on the order detail page.	WHO CALLED
Show attention name	If selected, this option will show the attention name on the order detail page header strip.	true
Attention display name	This value contains the display name for the attention field if shown on the order detail page.	ATTENTION
Show signed by name	If selected, this option will show the signed by name on the order detail page header strip.	true
Signed by display name	This value contains the display name for the signed by field if shown on the order detail page.	SIGNED BY
Show sales rep ID	If selected, this option will display the sales rep ID on the order detail page header strip.	true
Sales rep display name	This value contains the display name for the sales rep field if shown on the order detail page.	SALES REP
Show order taker ID	If selected, this option will display the order taker ID on the order detail header strip.	true
Order taker display name	This value contains the display name for the order taker field if shown on the order detail page.	ORDER TAKER
Show AAAA specials	If selected, the AAAA specials will be shown on the order detail page.	true
Show line item specials	If selected, the line item specials (comments) will be shown on the order detail page.	true
Show ZZZZ specials	If selected, the ZZZZ specials will be shown on the order detail page.	true
Show ship quantities for status 0	This value determines if ship quantities are shown to the user for orders in status 0.	false
Show ship quantities for status 1	This value determines if ship quantities are shown to the user for orders in status 1.	false
Show ship quantities for status 2	This value determines if ship quantities are shown to the user for orders in status 2.	false
Show ship quantities for status 3	This value determines if ship quantities are shown to the user for orders in status 3.	false

Order detail page options

Name	Description	Default Value
Show ship quantities for status 4	This value determines if ship quantities are shown to the user for orders in status 4.	false
Show ship quantities for status 5	This value determines if ship quantities are shown to the user for orders in status 5.	false
Show ship quantities for status 6	This value determines if ship quantities are shown to the user for orders in status 6.	false
Show ship quantities for status 7	This value determines if ship quantities are shown to the user for orders in status 7.	false
Show ship quantities for status 8	This value determines if ship quantities are shown to the user for orders in status 8.	false
Show ship quantities for status 9	This value determines if ship quantities are shown to the user for orders in status 9.	false
Show ship quantities for status A	This value determines if ship quantities are shown to the user for orders in status A.	false
Show ship quantities for status B	This value determines if ship quantities are shown to the user for orders in status B.	true
Show item pop-up details on order page	When selected, this will show a link to the item details pop-up on the order display page.	false